

November 2017



Xerox[®] DocuShare[®] Installation Guide



©2017 Xerox Corporation. All rights reserved. DocuShare®, Xerox®, and Xerox and Design® are trademarks of Xerox Corporation in the United States and/or other countries. BR15526

Apple®, Mac®, OS X® and Safari® are trademarks of Apple Inc., registered in the U.S. and other countries. Google® and Chrome™ are trademarks of Google, Inc. Microsoft®, Active Directory®, Internet Explorer®, SQL Server® and Windows® are trademarks of Microsoft Corporation in the United States and/or other countries. Firefox® and Mozilla® are trademarks of the Mozilla Foundation in the United States and/or other countries. Oracle® and Java® are trademarks of Oracle and/or its affiliates. PostgreSQL® is a trademark of the PostgreSQL Global Development Group. Red Hat® Enterprise Linux® is a trademark of Red Hat, Inc. in the US and other countries. VMware ESXi™ is a trademark of VMware in the United States and certain other countries.

Publication Date: November 2017.

This document supports DocuShare Release 7.0.

Table of Contents

1	Before you begin installation	6
	DocuShare license information.....	6
	DocuShare technical support.....	6
	System requirements	7
	Minimum server requirements	7
	DocuShare and DocuShare Education.....	7
	DocuShare Enterprise	8
	DocuShare Express.....	9
	DocuShare Web Client requirements (all product editions)	9
	Information required for DocuShare installation	11
	Software installed.....	12
	Importing an SSL certificate into DSTrustStore	14
2	DocuShare on a Windows platform	16
	Installation logs.....	16
	Install DocuShare	16
	Before you begin.....	16
	Start the installation	16
	Finish the installation	17
	License the site	18
	Uninstall DocuShare	20
	Uninstall SQL Server Express database	20
	Upgrade DocuShare	22
	System requirements review.....	22
	Installation logs.....	22
	Before you start the upgrade procedure.....	22
	Start the upgrade	23
	Finish the upgrade	24
	License the site	24
	Post upgrade tasks.....	24
	Update DocuShare software or add a language	26
	Install a software update.....	26
	Install a language.....	26
3	DocuShare on a Solaris platform.....	28
	Installation logs	28
	Install DocuShare	28

Before you begin.....	28
Start the installation	29
Finish the installation	29
License the site	30
Uninstall DocuShare	31
Upgrade DocuShare	31
System requirements review.....	31
Installation logs.....	31
Before you start the upgrade procedure.....	32
Start the upgrade	33
Finish the upgrade	33
License the site	34
Post upgrade tasks	34
Update DocuShare software or add a language	36
Install a software update.....	36
Install a language.....	36
4 DocuShare on a Linux platform.....	38
Installation logs	38
Install DocuShare	38
Before you begin.....	38
Start the installation	39
Finish the installation	40
License the site	40
Uninstall DocuShare	41
Upgrade DocuShare	42
System requirements review.....	42
Installation logs.....	42
Before you start the upgrade procedure.....	42
Start the upgrade	43
Finish the upgrade	44
License the site	44
Post upgrade tasks	45
Update DocuShare software or add a language	46
Install a software update.....	46
Install a language.....	46
5 Database configuration.....	48
Oracle.....	48
On the Oracle side	48
Connect role	48
On the DocuShare side	49

SQL Server.....	51
On the SQL Server side	51
On the DocuShare side	51
PostgreSQL.....	52
Windows platform	52
On the PostgreSQL side.....	52
On the DocuShare side	52
Solaris platform	52
On the PostgreSQL side.....	52
On the DocuShare side	53
Linux platform	53
On the PostgreSQL side.....	53
On the DocuShare side	53
6 Web server bridge.....	54
Create a bridge to an Apache web server	54
Create a bridge to an IIS web server.....	54
File upload problems using IIS with the DocuShare desktop applications	55
7 Add-on installation.....	56
OCR (Optical Character Recognition)	56
Installing OCR software	56
Additional languages for OCR	57
Xerox ConnectKey for DocuShare	57
Archive Server	57
Install the Archive Server	58
Configure client sites to use the Archive Server	58
Uninstall the Archive Server.....	58
Document Viewer	59
System requirements.....	59
DocuShare server	59
PrizmDoc server.....	59
Steps for the Document Viewer installation	60
1 - Install the PrizmDoc Server software	60
Installation on a Windows server	60
Installation on a Linux server	60
2 - Install the Document Viewer hotfix	61
3 - Install the Document Viewer add-on	61
Installation on a Windows server	61
Installation on a Linux server	62

Before you begin installation

This chapter contains the system requirements and installation information that you need to install or upgrade a DocuShare site. Before you begin an installation, read this chapter to make sure your server meets minimum requirements and that you are prepared with the information required by the install Wizard.

DocuShare license information

- If your installation is a 30 day trial; at the end of the installation, go to the Server License Management page of the Admin UI and click the “click here” link to apply for a trial license. This link does not appear if your site is already licensed.
- If your installation is a non-trial version of DocuShare, if you are upgrading your site, or you have purchased an add-on, Xerox DocuShare or your DocuShare reseller will provide instructions for obtaining a license.

DocuShare technical support

Your site is covered by DocuShare technical phone support for 30 days from the date you obtained a license. To purchase extended support, contact DocuShare sales.

System requirements

Note: Before installing or upgrading, go to docushare.xerox.com for the latest system requirements.

Minimum server requirements

DocuShare and DocuShare Education

Intel or AMD platforms

- Windows 2008 Server R2 SP1 Standard and Enterprise (64 bit)
- Windows 2012 Server R2 Standard and Datacenter (64 bit)
- Red Hat Enterprise Linux 6 Update 6 or higher (64 bit)
- Red Hat Enterprise Linux 7 (64 bit)
- Dual 3.0 GHz processor or better (IA-32 or x64)
- 4 GB RAM or higher
- 20 GB of free disk space
- Ethernet network interface

Sun SPARC platform (DocuShare Education only)

- Solaris 10 1/13
- UltraSPARC III processor or better
- 4 GB RAM or higher
- 20 GB of free disk space
- Ethernet network interface

Virtual server

- VMware ESXi 5.5 Update 2 or higher Server

An average use installation requires for each virtual server; a minimum of 4 GB virtual memory and 40 GB of free disk space for the operating system and DocuShare software.

If a database and stored documents are on the same virtual server; a minimum of 8 GB virtual memory and 200 GB of free disk space.

A high use installation requires for each virtual server; a 64 bit OS, 16 GB virtual memory, and 2 TB of free disk space.

Web servers

- IIS 7.5 on Windows 2008 Server
- IIS 8.5 on Windows 2012 Server R2
- Apache

Note: To connect DocuShare with Microsoft IIS 8 (included with Windows 2012 Server), refer to the DocuShare Knowledge Base article 1288 in the Web Servers category.

Databases

- Microsoft SQL Server 2008 R2 SP3 (64 bit)
- Microsoft SQL Server 2012 SP2 (64 bit)
- Microsoft SQL Server 2014 Express Edition (64 bit)
- Microsoft SQL Server 2014 (64 bit)
- Oracle 11.2
- Oracle 12c Release 1
- PostgreSQL 9.3.8

Note: Database connectors are required for Microsoft SQL Server and Oracle databases.

LDAP

- Sun Java Directory Server Enterprise Edition 6.3.1 or higher
- Microsoft Active Directory

DocuShare Enterprise**Intel or AMD platforms**

- Windows 2008 Server R2 SP1 Standard and Enterprise (64 bit)
- Windows 2012 Server R2 Standard and Datacenter (64 bit)
- Red Hat Enterprise Linux 6 Update 6 or higher(64 bit)
- Red Hat Enterprise Linux 7 (64 bit)
- Dual 3.0 GHz processor or better (IA-32 or x64)
- 8 GB RAM or higher
- 40 GB of free disk space
- Ethernet network interface

Sun SPARC Platform

- Solaris 10 1/13
- UltraSPARC III processor or better
- 8 GB RAM or higher
- 40 GB of free disk space
- Ethernet network interface

Virtual Server

- VMware ESXi 5.5 Update 2 or higher Server

An average use installation requires for each virtual server; a minimum of 4 GB virtual memory and 40 GB of free disk space for the operating system and DocuShare software.

If a database and stored documents are on the same virtual server; a minimum of 8 GB virtual memory and 200 GB of free disk space.

A high use installation requires for each virtual server; a 64 bit OS, 16 GB virtual memory, and 2 TB of free disk space.

Web servers

- IIS 7.5 on Windows 2008 Server
- IIS 8 on Windows 2012 Server
- SunONE/ Sun Java System Web Server 6.1 on Solaris 10
- Apache Web Server

Note: To connect DocuShare with Microsoft IIS 8 (included with Windows 2012 Server), refer to the DocuShare Knowledge Base article 1288 in the Web Servers category.

Databases

- Microsoft SQL Server 2008 R2 SP3 Enterprise Edition
- Microsoft SQL Server 2012 SP2 Enterprise Edition
- Microsoft SQL Server 2014 Express Edition
- Oracle 11.2
- Oracle 12c Release 1

LDAP

- Sun Java Directory Server Enterprise Edition 6.3.1 or higher
- Microsoft Active Directory

DocuShare Express

Note: DocuShare Express is not available in all geographies.

- Windows 2008 Server R2 SP1 Standard and Enterprise (64 bit)
- Windows 2012 Server R2 Standard and Datacenter (64 bit)
- Dual 3.0 GHz processor or better (IA-32 or x64)
- 3 GB RAM or higher
- 20 GB of free disk space
- Ethernet network interface

DocuShare Web Client requirements (all product editions)

Web browsers

- Microsoft Internet Explorer 10
- Microsoft Internet Explorer 11
- Mozilla Firefox: latest ESR
- Apple Safari: latest on OSX and iOS
- Google Chrome: latest

WebDAV

- Apple Mac OS X 10.10

Information required for DocuShare installation

The install Wizard asks questions about how you want the site installed. You may accept the defaults, but there is some required information that you should have before starting the installation. After installation, the administrator of the site can change most of the information that was provided during installation.

Information that you need for an installation include:

- Web server installation information:
 - Windows platform: If you choose to use Microsoft IIS as your web server, load IIS during Windows Server software installation.

Note: When installing IIS on Windows 2008 and Windows 2012, deselect the WebDAV Publishing feature. WebDAV running with DocuShare will not work if this feature is selected.

Choose **Tomcat interacts with IIS** from the DocuShare Wizard Web Server Interaction window. This choice installs the DocuShare Tomcat servlet engine and the software that connects the Tomcat engine to the IIS web server. If you choose to install Tomcat with IIS, you need to declare an IIS port number to use if you do not accept the default port number.

If you choose to install a web server other than IIS, you must follow the installation instructions for that web server. The web server must be installed and running before you begin the DocuShare software installation. In this case, choose **Tomcat only** from the Web Server Interaction window.



Caution

WebDAV does not work if your DocuShare site is set up to use IIS via the Tomcat/IIS bridge connection. Your site must be configured to use an Apache server. See the Web Server Bridge chapter of this guide for information on creating a bridge to an Apache server.

- Refer to the Web Server Bridge section of this guide for instruction on how to edit specific files to create a bridge between your web server and the Tomcat servlet.
- Web server options:

You can later change these settings by using dssetup. Refer to the *DocuShare Command Line Utilities Guide* for more information and instructions on use.

 - A fully qualified DNS hostname (such as *sales.acme.com*) or the IP address for the server. You cannot use aliases or WINS names.
 - The server root (the default is docushare).
 - Whether you want to run the server as HTTP or HTTPS. Choose HTTPS only if you configured your web server for HTTPS service.
- Database installation information:
 - If you choose to install the default Microsoft SQL Express database, you can accept the default database port number or enter one of your own.

- If you choose to install a different database, refer to the Database Configuration section of this guide for installation information.
- Crucial ports and pathnames:
You can later change these settings by using dssetup. Refer to the *DocuShare Command Line Utilities Guide* for more information and instructions on use.
 - A designated port for the Tomcat servlet (default port=8080)
 - A designated port for the RMI server (default port=1099)
 - A designated location for document repository
 - A fully qualified DNS name for the SMTP mail server
 - A designated port for the SMTP server (default port=25)
 - A designated port for the Tomcat Web Bridge (default port=8009)
 - A designated port for the Tomcat Web servlet (default port=8005)
- What type of DocuShare installation you want installed:
 - DocuShare with FTP scan feature. This installation installs SMB scan service and an FTP scan service to receive documents. Make sure your site security rules allow the use of FTP.
 - DocuShare without FTP scan feature. This installation installs only SMB scan service.
 - DocuShare Archive Server. This installation installs the Archive Server software.
- What type of user can access the site; Guest (anyone), User (only registered users), or Administrator (only registered administrators).
- Who can create new user accounts on the site; Guests, Registered Users, or Administrators.
- Who can create new group accounts on the site; Registered Users or Administrators.
- The default user level that is assigned to all new user accounts; Read-only, DocuShare User, or CPX User. User levels are license dependent, so the CPX level is available only if your site is licensed for CPX users.
- How do you want to display dates; US English (mm/dd/yy) or International English (dd/mm/yy).
- A unique site admin password and the email address of the site administrator.
- A location on your server where you want the Wizard to install the DocuShare software. The path to the DocuShare install directory must be made up of ASCII characters. The path cannot contain multi-byte characters.
- For Windows platforms, decide how you want to control stopping and starting DocuShare; either AutoStart or manually through the Services window.

Software installed

The following software is installed along with the DocuShare 7 server software:

- DocuShare Print and Email
- Xerox DocuShare Application Connector

- Xerox ConnectKey for DocuShare (Windows platform only)

Note: ConnectKey for DocuShare requires configuration. See the Xerox ConnectKey for DocuShare Setup Guide located on the Help Desk. If your site uses an Apache web server, follow the steps in the Configuration file modification for Apache web server section in the Xerox ConnectKey for DocuShare Setup Guide to enable the ConnectKey pages in the Admin UI.

- Default database (option to use is selectable during installation)
- Language packs (languages to use are selectable during installation)

Importing an SSL certificate into DSTrustStore

If the site requires Secure Socket Layer (SSL), you must import a certificate to the DSTrustStore file in DocuShare.

To place the certificate .cer file into the DSTrustStore file:

1. Copy the .cer file to the DocuShare directory containing the DSTrustStore file **jdk\jre\lib\security**.
2. Open a command prompt window and navigate to the directory containing **dstruststore**.

```
C:\>CD\Xerox\Docushare\jdk\jre\lib\security
C:\Xerox\DocuShare\jdk\jre\lib\security>dir
Volume in drive C is Local Disk
Volume in Serial Number is 508B-0D2F
Directory of C:\Xerox\DocuShare\jdk\jre\lib\security

18-11-02   15:55           <DIR>          -
18-11-02   15:55           <DIR>          --
02-10-02   12:25                7,365 cacerts
02-10-02   12:26                589 dstruststore
02-10-02   12:26                2,271 java.policy
02-10-02   12:26                4,115 java.security
10-11-02   15:43                844 SLL_Cert4LDAP.cer

           5 File(s)              15,184 bytes
           2 Dir(s)      1,486,024,704 bytes free
```

```
C:\Xerox\DocuShare\jdk\jre\lib\security
```

3. At the command prompt, enter the **set PATH** command to set the PATH environment variable. Use set **PATH=%PATH%;<your DocuShare directory>\jdk\jre\bin**.

```
C:\Xerox\DocuShare\jdk\jre\lib\security>set
PATH=%PATH%;C:\Xerox\DocuShare\jdk\jre\bin
```

4. After you have set the PATH variable, at the command prompt, enter **keytool**, without arguments.

The Keytool Utility help appears. The Keytool Utility places the SSL certificate in the DSTrustStore.

5. At the command prompt, enter the keytool utility command **keytool -import -alias <alias_name> -file <cert_file> -keystore dstruststore**
 - a. Replace **<alias_name>** with a unique name for the certificate file.
 - b. Replace **<cert_file>** with the name of the certificate file (.cer) that you exported and copied to the directory containing the dstruststore file.
6. Press **Enter** to start the command.

A request for a password appears.
7. Enter **password** and press **Enter**.

```
C:\Xerox\DocuShare\jdk\jre\lib\security>keytool -import -alias Test
LDAPss1 -file SDL_Cert4LDAP.cer -keystore dstruststore
Enter keystore password: password
Owner: OU=EFS File Encryption Certificate, L=EFS, CN=Administrator
Issuer: OU=EFS File Encryption Certificate, L=EFS, CN=Administrator
Serial number: 5ee8abd44c2cd2b14ffbee159f03d354
Valid from: Tue Feb 19 10:57:21 PST 2012 until: Thu Jan 26 10:57:21
PST 2102
Certificate fingerprints:
    MD5: 78:C7:A3:04:32:69:EB:97:76:FE:F4:8A:11:A2:65:26
    SHA1:
02:DD:9A:BE:BE:DE:3C:AA:22:AE:14:9A:F2:F2:5B:11:61:6D:5A:5F
Trust this certificate? [no]: yes
Certificate was added to keystore
C:\Xerox\DocuShare\jdk\jre\lib\security>
```

8. Examine the screen output to ensure that Keytool successfully added the certificate to the keystore. If Keytool completed the operation, your DocuShare server is now ready to use the certificate for SSL.
9. Once you have finished importing the certificate, reboot your DocuShare server.

DocuShare on a Windows platform

Installation logs

The DocuShare installer records all initial installation activity in **InstallLog.txt**. After the installer creates the DocuShare directory, it creates a **DocuShareInstallLog.txt** file in the home directory where it stores the remaining installation data.

To save the initial InstallLog file, start the installation process in a command prompt window by entering the command: **docushare.exe -P docushareLog.cleanUp=false**.

To view the saved InstallLog file; open a command prompt window, cd to **%temp%** and enter **>dir**.

Install DocuShare

Before you begin

1. Review Chapter 1 of this guide to make sure your server meets the minimum requirements for DocuShare installation and that you have gathered the information required by the install Wizard.
2. If you have chosen not to install the DocuShare supplied web server, make sure you have installed and configured the web server of your choice, and that web server is running before you begin DocuShare installation.
3. If you have chosen not to install the DocuShare default database, make sure you have installed and configured the database of your choice, and that database is running before you begin DocuShare installation.
4. For an easier installation, we recommend that you install DocuShare on a clean server; one with newly installed operating system software.
5. If you have other instances of DocuShare running on the same server, make sure those instances are running before installing additional instances. Failure to do so can later result in indexing problems and in situations where stopping one instance of DocuShare stops all instances.

Start the installation



Caution

If you have other instances of DocuShare running on the same server, make sure those instances are running before installing additional instances.

1. Log into the server using the Windows local server administrator account.

2. Download the DocuShare software to a temporary directory on your server and unzip the file.
3. Open the file, locate and double-click **docushare.exe**.
Be patient; it takes several minutes before the system displays the first install Wizard screen.
4. Follow the onscreen instructions; accept the defaults or enter your own configuration information.
5. Click **Next** to advance the installation or click **Back** to return to a previous page to make a change.

Before the installer loads DocuShare, the Wizard allows you to make changes to your choices. After installation, the administrator of the site has the authority to change most of the information that was provided during installation; using either the Admin UI or a command prompt window.

6. In the database configuration window, select a database option then click **Next** and enter the configuration information for your database.

If you selected Oracle 12c, add **c##** to the beginning of the user name in the **Database User** field. For example; **c##lq661b110**.

If you selected the SQL Server Express database, enter a Database User Password (at least eight characters, with a mix of upper/lower case and numbers, select Named Instance to create a new database, and select **Install SQL Express**.

7. In the Web Server Interaction window, select how you want the web server to connect with the Tomcat servlet engine.
 - Select **Tomcat interacts with IIS** if you installed IIS as part of your operating system software and want to use IIS as your web server.
 - Select **Tomcat only** if you installed a web server other than IIS. At the end of the installation, you will have to manually edit some files to connect the web server to the Tomcat servlet.

Note: If you later want to use IIS as your web server, refer to [Create a bridge to an IIS web server](#) on page 54 of this guide.

8. In the Windows service setup window, select **Install the DocuShare Windows Service**.
Running DocuShare as a service on your Windows server is recommended. If your DocuShare server is in a clustered environment, do not select DocuShare Windows Service Auto Start; the clustered resource group will start DocuShare.
9. Select the languages you want installed with DocuShare. Follow the instructions displayed on the wizard screen to add additional languages to the displayed choices.
10. Review the installation summary, make any necessary changes, then click **Next** to start the installation.

Finish the installation

1. When the installation successfully completes, click **Finish** to close the installer.
2. Reboot the server.
3. If you selected Tomcat only, refer to Web Server Bridge chapter of this guide to edit specific files to create a bridge between your web server and the Tomcat servlet.

4. After the server restarts; if you selected DocuShare with FTP scan feature, use the IIS Manager to disable the IIS FTP service.
5. If you did not set DocuShare to run as an autostart service, do **one** of the following:
 - Enter **<DSHome>\bin\start_docushare** in a command prompt window to start DocuShare.
 - In the Administrative Tool, in the Services application, select and **start** the DocuShare service.

DocuShare initial startup automatically updates the search indexes; allow five minutes before attempting to connect to the site through a browser.

6. If the site uses SSL and you selected IIS as your web server, follow these instructions to close the Tomcat servlet port to prevent unauthorized access to the Tomcat web servlet through that port.
 - a. Stop DocuShare by entering the command, **stop_docushare**.
 - b. Run the dssetup command **and** change the status of the Tomcat http port to off.
 - c. Start DocuShare by entering the command, **start_docushare**.
 - d. Reboot the system if you are using IIS.

License the site

1. Use a browser to connect to your newly installed site.
 - The default URL is `http://<fully qualified DNS name>:8080/docushare`.
 - If DocuShare was installed in the home directory on your web site, the URL is: `http://<fully qualified DNS name>:<port>/`
 - If DocuShare was installed in a subdirectory on your web site, the URL is: `http://<fully qualified DNS name>:<port>/virtual web directory name/`
 - If you installed IIS on your server, then the `:<port>` component of the URL is not used. For example: `http://<fully qualified DNS name>/docushare`
 - If you installed only Tomcat on your server, then the `:<port>` component of the URL is 8080 (default).
 - If you changed the server root to **root** during the installation, the `/docushare` (default) component of the URL is not required. For example, `http://<fully qualified DNS name>` or `http://<fully qualified DNS name>:8080`
2. Use the admin password you set during installation and log into the site as *admin*.
3. On the navigation bar, click **Admin Home**.
4. From the Administration menu, click **Site Management | License**.
5. On the License page, locate and write down the **Host ID** number exactly as displayed.
6. Follow the instructions that Xerox DocuShare or your DocuShare reseller provided to obtain a site license string.
7. When you have the license string, return to the **Site Management | License** page and enter the string in the **License** field.

8. Refer to the *Administrator Guide* for information on post-installation site configuration, such as setting up your site to use SSL.

Uninstall DocuShare

If you select to retain the content store, the uninstall Wizard does not remove the DocuShare directory that includes your DocuShare repository content. To be safe, before uninstalling DocuShare move the repository content to another storage media by using the DocuShare command line utility, **dsexport**. Refer to the *DocuShare Command Line Utilities Guide* for details.

Uninstall removes all installed language packs.



Caution

The DocuShare uninstaller only removes DocuShare, not the installed database. You should back up data for all Windows applications sharing the database. If you are using the SQL Server Express database, back up all data to a secure location.

To uninstall DocuShare:

1. In **Administrative Tools**, select and open the **Services** application.
2. Select **DocuShare**, and then select **STOP** the service.
3. In the **Control Panel**, select and open **Add/Remove (Programs and Features)** if the site is running on a Windows 2008 Server platform).
4. Scroll and select **DocuShare**, click **Remove**, and then follow the onscreen instructions.
5. After Add/Remove uninstalls DocuShare, manually delete the directory where DocuShare was installed.

Uninstall SQL Server Express database

The uninstall Wizard does not remove the installed SQL Server Express database. After you have uninstalled and removed all DocuShare files, follow this procedure to remove the SQL Server Express database files.

Note: Before you begin, refer to the Microsoft website for any updated uninstall instructions.

1. If you have not done so already, **back up all data in the database to a secure location.**
2. In the Control Panel, select and open the **Add/Remove** application.
3. Select **Microsoft SQL Server 2014**, then click **Remove**.
4. The Component Selection page appears; select **Remove SQL Server 2014 instance components**.
5. Select **Workstation Components**.
6. The Confirmation page appears, listing the components to remove.
7. Click **Finish** to complete the SQL Server Express uninstall.
8. Then the process has completed, you must now remove the SQL Native Client.
9. In the **Control Panel**, select and open the **Add/Remove** application.
10. Select **Microsoft SQL Native Client**, then click **Remove**.

11. A window appears asking you to confirm the removal of the SQL Native Client, click **Yes**.
The SQL Server Express software and Native Client are removed from your drive.

Upgrade DocuShare

If you are upgrading from DocuShare 6.5.3 or earlier, upgrade to DocuShare 6.6.1 R2 before upgrading to DocuShare 7. If you are upgrading from DocuShare 6.6.1, upgrade to DocuShare 6.6.1 Update 2 before upgrading to DocuShare 7. If you are upgrading from DocuShare 6.6.1 R2 or 6.6.1 Update 2 or later, you can upgrade directly to DocuShare 7.

A DocuShare upgrade utility is included with the software install Wizard. The utility can take sites as low as version 5.0.3 and upgrade them to the current version of DocuShare.

System requirements review

Before making any DocuShare upgrades, review the system requirements for the upgrade version, and make sure your server meets those requirements. Look carefully at the operating system, database, web server, memory and disk space requirements for the upgrade.

Installation logs

The DocuShare installer records all upgrade activity and stores it in the DocuShareInstallLog.txt file.

Before you start the upgrade procedure

- A day prior to upgrading the site, inform users that the site will be down
 - a. Go to **Site Management | Site Operations**.
 - b. In the **Admin Message** field, enter a message telling users when the site will be unavailable and for how long; then select **Yes** in the **Show Admin Message** field.
 - c. Click **Apply**.
- Review the information required for DocuShare software installation presented in Chapter 1. Record all of your current configuration settings so you can enter them in the upgrade Wizard windows.
- From the Administration menu, click **Site Management | License**. On the **License** page, locate and write down the **Host ID** number of the server.
- Stop all automated or programmatically generated activities; especially those that use the Content Intake Manager, Content Rules, or Scan to DocuShare services.
- Close site access
 - a. Log into the DocuShare site as *admin*.
 - b. Go to **Site Management | Access Policies**.
 - c. Set the **Site Access Authority** to Administrator, then click **Apply**.
 - d. Go to **Site Management | Site Operations**.
 - e. In the **Admin Message** field, enter a message telling users that the site is going down in ten minutes, select **Yes** in the **Show Admin Message** field, then click **Apply**.
 - f. After ten minutes, enter the message *DocuShare is currently in read-only mode* in the **Admin Message** field.

- g. In the **System Mode** field, select **Read Only**.
- h. In the **Show Admin Message** field select **Yes**.
- i. Click **Apply**.
- Close all Windows applications that are currently open on the server.
- Backup the IDOL database
 - a. Make sure the target directory exists and is empty before starting backup. The target directory is represented as <exportdir> in the command.
 - b. Run the command **idoltool.bat -s export <exportdir>**.
- Clear the event queue
 - a. Go to **Site Management | Site Operations**.
 - b. In the **System Mode** field, select **Read Write** and select **No** in the **Show Admin Message** field; then click **Apply**.
 - c. Go to **Services and Components | Subscription**.
 - d. Set the **Weekly Notification Day** to the current day of the week, and set the **Weekly Notification Hour** and **Weekly Notification Minute** to five minutes from the current time; then click **Apply**.
 - e. Wait ten minutes before proceeding with the upgrade.
 This allows the DocuShare notification service to send all subscribed notifications and clear the event queue. Failure to clear the event queue before starting the upgrade results in the lost of all events waiting in the queue.
- Stop DocuShare
 - a. Log into the server using the Windows local server administrator account.
 - b. In the Administrator Tool, select and open the Services application, select **DocuShare** and **stop** the service.
- Backup the site database
 - a. In your database server manager, stop the database.
 - b. Perform a system backup of your DocuShare site.
 - c. When the backup is finished, start the database.
 - d. The database must be running for the DocuShare Installer to upgrade the database schema.
 - e. If you are using a Microsoft SQL Server database, run **exec sp_fulltext_database enable** on the server to enable full text search.

Start the upgrade

1. Download the DocuShare software to a temporary directory on your server and unzip the file.
2. Open the file, locate and double-click **docushare.exe**.

3. Be patient; it takes several minutes before the system displays the first install Wizard screen.

Note: If you want the installer to save all configuration and upgrade data, start the upgrade in a command prompt window by entering the command line: `docushare.exe -P docushareLog.cleanUp=false`.

4. When the Upgrade Option window appears, select the appropriate **Upgrade**.
Be patient; it takes several minutes for the system to load and start the installer.
5. Follow the onscreen instructions; accept the defaults or enter your own configuration information.

Finish the upgrade

1. When the upgrade successfully completes, click **Finish** to close the installer.
2. Reboot the server.
3. After the server restarts, if you did not set DocuShare to run as an autostart service, do **one** of the following:
 - Enter `<DSHome>\bin\start_docushare` in a command prompt window to start DocuShare.
 - In the Administrative Tool, in the Services application, select and **start** the DocuShare service.
4. If your DocuShare site uses LDAP over a secure SSL channel, you need to import the SSL certificate into the newly installed **dstrust store**. Instructions for importing the LDAP SSL Certificate are in the *LDAP Active Directory Guide* that is located on the Help page of your DocuShare site.
5. The DocuShare Installer stops the IIS service during the upgrade and restarts it at completion. If the installer does not restart the IIS service, open a command prompt window and enter: **net start w3svc**.

License the site

1. Use a browser to connect to your newly upgraded site and login as *admin*.
2. From the Administration menu, click **Site Management | License**.
3. On the License page, locate and write down the **Host ID** number exactly as displayed.
4. Follow the instructions that Xerox DocuShare or your DocuShare reseller provided to obtain a site license string.
5. When you have the license string, return to the **Site Management | License page** and enter the string in the **License** field. Do not use your old site license nor a trial license.

Post upgrade tasks

1. Reset user levels for all user accounts on your site. If you upgraded from DocuShare 5.x, all user accounts are now set to the CPX level. You must now activate and set each account to either Read-Only or DocuShare user levels as appropriate.

Refer to the *DocuShare Administrator Guide* for information on user levels and changing user levels through **Account Management | Users | Change User Level**.

2. Run database optimization as defined in the *DocuShare Administrator Guide* database optimization procedures.
3. To access customized VDF and image files, the upgrade installer relocates these files to <DSHome>\DSUpgrade\BackUpDir.0\amber.jar and <DSHome>\DSUpgrade\BackUpDir.0\root.jar.

Note: VDF files customized to work with DocuShare 5.x or older are not upgraded by the installer and do not work with this release of DocuShare. Refer to the DocuShare VDF Reference Guide to migrate your custom VDFs to the current DocuShare release.

4. If you changed the Subscription Notification settings to clear the event queue, go to the **Services and Components | Subscription** administration page and return the **Weekly Notification Day, Hour, and Minute** to their values prior to the upgrade.
5. Go to **Site Management | Access Policies**.
6. Return the **Site Access Authority** to the pre-upgrade setting, then click **Apply**.

Update DocuShare software or add a language

Patches, updates, and additional languages for DocuShare software, when available, are easily installed using the DocuShare update wizard.

- Before you install software updates, make sure the selected update is compatible with your version of DocuShare. Go to **About DocuShare**, on your site home page or in the Administration Menu, to locate your version number.
- If documentation is supplied with an update, read the documentation before starting the installation.

Install a software update

1. Log into the DocuShare server as a Windows administrator.
2. In a command prompt window, cd to **<DSHome>/bin** and enter **stop_docushare.bat -q**.
3. Download, or copy, the software to a temporary directory on your server and unzip the file.
4. Open the file, then locate and double-click **dsUpdate.exe**.
Be patient; it takes several minutes before the system displays the first install Wizard screen.
5. Once the install Wizard begins, follow the onscreen instructions. Click **Next** to proceed or click **Back** to return to a previous screen.
6. When asked to select an update, check the appropriate update, or browse to the location of the update **jar** file, click **Add Update**, then click **Next** to start the installation.
7. When the installation successfully completes, click **Finish** to close the installer.
8. In a command prompt window, cd to **<DSHome>/bin** and enter **start_docushare.bat** to start DocuShare or **start_docushare.bat console** to see the log to the console.
9. Use a browser to connect to your site, and log in as an administrator.
10. If your specific update requires a new license, obtain a site license string and apply it to the **License** field on the **Site Management | License** page.

Install a language

1. Log into the DocuShare server as a Windows administrator.
2. In the Windows Administrator Tool, select and open the Services application, select **DocuShare** and **stop** the service.
3. Open the DocuShare software folder (not the installed software folder), locate and double-click **dsUpdate.exe**.
Be patient; it takes several minutes before the system displays the first install Wizard screen.
4. When asked to select a language, check the appropriate language, and then click **Next** to start the installation.
5. When the installation successfully completes, click **Finish** to close the update installer.
6. Restart DocuShare.

7. Go to **Site Management | Installed Languages** to make any changes in your default and installed language choices.

DocuShare on a Solaris platform

Installation logs

The DocuShare installer records all initial installation activity and stores it in **InstallLog.txt** in the **/var/tmp** directory of your server. After the installer has created the DocuShare directory, it creates a second **DocuShareInstallLog.txt** file in the home directory; where it stores the remaining installation information.

To save the initial InstallLog file, start the installation process in a command prompt window by entering the command: **./docushare -P docushareLog.cleanUp=false**.

Install DocuShare

Before you begin

1. Review Chapter 1 of this guide to make sure your server meets the minimum requirements for DocuShare installation and that you have gathered the information required by the install Wizard.
2. If you have chosen not to install the DocuShare supplied web server, make sure you have installed and configured the web server of your choice, and that web server is running before you begin DocuShare installation.
3. If you have chosen not to install the DocuShare supplied database, make sure you have installed and configured the database of your choice, and that database is running before you begin DocuShare installation.
4. For an easier installation, we recommend that you install DocuShare on a clean server; one with newly installed operating system software.
5. If you have other instances of DocuShare running on the same server, make sure those instances are running before installing additional instances. Failure to do so can later result in indexing problems and in situations where stopping one instance of DocuShare stops all instances.

Start the installation



Caution

If you have other instances of DocuShare running on the same server, make sure those instances are running before installing additional instances.

1. Log into the server as a UNIX server administrator (root).
2. Download the DocuShare software to a temporary directory on your server and extract the tar file.
3. In a command prompt window go to **<DSHome>/<Solaris>/DocuShare** and enter **docushare**.
Be patient; it takes several minutes before the system displays the first install Wizard screen.
4. Follow the onscreen instructions; accept the defaults or enter your own configuration information.
5. Click **Next** to advance the installation or click **Back** to return to a previous page to make a change.

Before the installer loads DocuShare, the Wizard allows you to make changes to your choices. After installation, the administrator of the site has the authority to change most of the information that was provided during installation; using either the Admin UI or a command prompt window.

6. In the database configuration window, select a database option then click **Next** and enter the configuration information for your database.

If you selected Oracle 12c, add **c##** to the beginning of the user name in the **Database User** field. For example; **c##lq661b110**.

If you selected PostgreSQL, enter the Database User Password and select **Create Database**.

7. In the Web Server Interaction window, select **Tomcat only**.
8. In the UNIX Account Parameters window, enter the appropriate information.

The default is **nobody**, which allows any user with an UNIX account to login and start DocuShare.

If you installed scan to DocuShare, you must be logged in as root to start DocuShare and to enable the scan feature. For non-root users to enable the scan to DocuShare feature, the FTP server default port (port 21) must be changed to another port that is above port 1024 (ftpd.conf) and the Xerox Work Centres used for scanning must be able to specify this port.

Finish the installation

1. When the installation successfully completes, click **Finish** to close the installer.
2. Set your UNIX virtual display buffer to operate within an X Windows system.
DocuShare operates in an X Windows environment; set the display buffer to use all of the DocuShare features. In a headless system, an error occurs if the display buffer is not correctly set.
3. In a command prompt window, cd to **<DSHome>/bin**, then enter **./start_docushare.sh** to start DocuShare.

At initial startup, DocuShare automatically updates the search indexes. Wait five minutes before you access the site with a browser.

Note: To prevent the Search Service from stopping when you exit the shell, use either the `start_docushare.sh bg` or the `start_docushare.sh bg &` command to start DocuShare in background mode.

4. If you installed **Scan-to-DocuShare via FTP**, disable the UNIX FTP service on your UNIX system.

Note: If Scan-via-FTP is installed, you must be root to start DocuShare to enable the scan feature. To enable the Scan-via-FTP feature by non-root users, the FTP server default port (port 21) must be modified to another port above port 1024 (ftpd.conf) and the Xerox Work Centres must be able to specify this port.

- a. Log into the server as a UNIX server administrator (root).
- b. From the Start menu, select **Service Configuration**.
- c. In the Service Configuration window, de-select **wu-ftpd**.

License the site

1. Use a browser to connect to your newly installed site.
 - The default URL is `http://<fully qualified DNS name>:8080/docushare`.
 - If DocuShare was installed in the home directory on your web site, the URL is: `http://<fully qualified DNS name>:<port>/`
 - If DocuShare was installed in a subdirectory on your web site, the URL is: `http://<fully qualified DNS name>:<port>/<subdirectory_path>/`
 - If you installed Apache on your server, then the `:<port>` component of the URL is not used. For example: `http://<fully qualified DNS name>/docushare`
 - If you installed only Tomcat on your server, then the `:<port>` component of the URL is 8080 (default).
2. Use the admin password you set during installation and log into the site as *admin*.
3. On the navigation bar, click **Admin Home**.
4. From the Administration menu, click **Site Management | License**.
5. On the License page, locate and write down the **Host ID** exactly as displayed.
6. Follow the instructions that Xerox DocuShare or your DocuShare reseller provided to obtain a site license string.
7. When you have the license string, return to the **Site Management | License** page and enter the string in the **License** field.
8. Refer to the *Administrator Guide* for information on post-installation site configuration, such as setting up your site to use SSL.

Uninstall DocuShare

Uninstall does not remove the DocuShare directory that includes your DocuShare repository content. To be safe, before uninstalling DocuShare move the repository content to another storage media by using the DocuShare command line utility, **dsexport**. Refer to the *DocuShare Command Line Utilities Guide* for details.

Uninstall removes all installed language packs.



Caution

The DocuShare uninstaller only removes DocuShare, not the installed database. You should backup data for all Solaris applications sharing the database.

To uninstall DocuShare:

1. Log into the server as a UNIX server administrator (root).
2. Stop the DocuShare server by doing the following:
 - a. Open a command prompt window
 - b. Change the directory to **<DSHome>/bin**
 - c. Enter **./stop_docushare.sh**
3. Change the directory to **<DSHome>/_uninst**.
4. Enter **./doc_uninstall**, then follow the onscreen instructions.
5. After doc_uninstall uninstalls DocuShare, manually delete the directory where DocuShare was installed.

Upgrade DocuShare

If you are upgrading from DocuShare 6.5.3 or earlier, upgrade to DocuShare 6.6.1 R2 before upgrading to DocuShare 7. If you are upgrading from DocuShare 6.6.1, upgrade to DocuShare 6.6.1 Update 2 before upgrading to DocuShare 7. If you are upgrading from DocuShare 6.6.1 R2 or 6.6.1 Update 2 or later, you can upgrade directly to DocuShare 7.

A DocuShare upgrade utility is included with the software install Wizard. The utility can take sites as low as version 5.0.3 and upgrade them to the current version of DocuShare.

System requirements review

Before making any DocuShare upgrades, review the system requirements for the upgrade version, and make sure your server meets those requirements. Look carefully at the operating system, database, web server, memory and disk space requirements for the upgrade.

Installation logs

The DocuShare installer records all upgrade activity and stores it in the DocuShareInstallLog.txt file.

Before you start the upgrade procedure

- A day prior to upgrading the site, inform users that the site will be down
 - a. Go to **Site Management | Site Operations**.
 - b. In the **Admin Message** field, enter a message telling users when the site will be unavailable and for how long; then select **Yes** in the **Show Admin Message** field.
 - c. Click **Apply**.
- Review the information required for DocuShare software installation presented in Chapter 1. Record all of your current configuration settings so you can enter them in the upgrade Wizard windows.
- From the Administration menu, click **Site Management | License**. On the License page, locate and write down the **Host ID** number of the server.
- Stop all automated or programmatically generated activities; especially those that use the Content Intake Manager, Content Rules, or Scan to DocuShare services.
- Close site access
 - a. Log into the DocuShare site as *admin*.
 - b. Go to **Site Management | Access Policies**.
 - c. Set the **Site Access Authority** to Administrator, then click **Apply**.
 - d. Go to **Site Management | Site Operations**.
 - e. In the **Admin Message** field, enter a message telling users that the site is going down in ten minutes, select **Yes** in the **Show Admin Message** field, then click **Apply**.
 - f. After ten minutes, enter the message *DocuShare is currently in read-only mode* in the **Admin Message** field.
 - g. In the **System Mode** field, select **Read Only**.
 - h. In the **Show Admin Message** field select **Yes**.
 - i. Click **Apply**.
- Backup the IDOL database
 - a. Make sure the target directory exists and is empty before starting backup. The target directory is represented as <exportdir> in the command.
 - b. Run the command `idoltool.sh -s export <exportdir>`.
- Clear the event queue
 - a. Go to **Site Management | Site Operations**.
 - b. In the **System Mode** field, select **Read Write** and select **No** in the **Show Admin Message** field; then click **Apply**.
 - c. Go to **Services and Components | Subscription**.
 - d. Set the **Weekly Notification Day** to the current day of the week, and set the **Weekly Notification Hour** and **Weekly Notification Minute** to five minutes from the current time; then click **Apply**.
 - e. Wait ten minutes before proceeding with the upgrade.

This allows the DocuShare notification service to send all subscribed notifications and clear the event queue. Failure to clear the event queue before starting the upgrade results in the lost of all events waiting in the queue.

- Stop DocuShare
 - a. Log into the server as a UNIX server administrator (root).
 - b. In a command prompt window, cd to **<DSHome>/bin** and enter **./dsservice.sh - shutdown DocuShare** to stop the server.
- Backup the site database
 - a. In your database server manager, stop the database.
 - b. Perform a system backup of your DocuShare site.
 - c. When the backup is finished, start the database.
The database must be running for the DocuShare Installer to upgrade the database schema.
 - d. If you are using a Microsoft SQL Server database, run **exec sp_fulltext_database enable** on the server to enable full text search.

Start the upgrade

To have DocuShare save all configuration and upgrade data, start the upgrade in a Command Prompt window by entering the command line: **docushare.exe -P docushareLog.cleanUp=false**

1. Log into the server as a UNIX server administrator (root).
2. Download the DocuShare software to a temporary directory on your server and extract the tar file.
3. In a command prompt window go to **<DSHome>/<Solaris>/DocuShare** and enter **docushare**.
4. When the Upgrade Option window appears, select **Upgrade**.
Be patient; it takes several minutes for the system to load and start the installer.
5. Follow the onscreen instructions; accept the defaults or enter your own configuration information.
6. If the Wizard detects that your current IDOL server is 32 bit, it will upgrade IDOL to the 64 bit version and prompt you to reindex the site after upgrading completes. Follow the *Index the site* procedure that is presented later in these upgrade instructions.

If the Wizard detects that your current IDOL server is 64 bit, it will silently upgrade IDOL to the latest 64 bit version, and you can skip the *Index the site* procedure.

Finish the upgrade

1. When the upgrade successfully completes, click **Finish** to close the installer.
2. Set your UNIX virtual display buffer to operate within an X Windows system.
DocuShare operates in an X Windows environment; set the display buffer to use all of the DocuShare features. In a headless system, an error occurs if the display buffer is not correctly set.

3. In a command prompt window, cd to **<DSHome>/bin**, then enter **./start_docushare.sh** to start DocuShare.

At initial startup, DocuShare automatically updates the search indexes. Wait five minutes before you access the site with a browser.

Note: To prevent the Search Service from stopping when you exit the shell, use either the **start_docushare.sh bg** or the **start_docushare.sh bg &** command to start DocuShare in background mode.

4. If you installed **Scan-to-DocuShare via FTP**, disable the UNIX FTP service on your UNIX system.

Note: If Scan-via-FTP is installed, you must be root to start DocuShare to enable the scan feature. To enable the Scan-via-FTP feature by non-root users, the FTP server default port (port 21) must be modified to another port above port 1024 (ftpd.conf) and the Xerox Work Centres must be able to specify this port.

- a. Log into the server as a UNIX server administrator (root).
 - b. From the Start menu, select **Service Configuration**.
 - c. In the Service Configuration window, de-select **wu-ftp**.
5. If your DocuShare site uses LDAP over a secure SSL channel, you need to import the SSL certificate into the newly installed **dsstrust store**. Instructions for importing the LDAP SSL Certificate are in the *LDAP Active Directory Guide* that is located on the Help page of your DocuShare server.

License the site

1. Use a browser to connect to your newly upgraded site and login as *admin*.
2. From the Administration menu, click **Site Management | License**.
3. On the License page, locate and write down the **Host ID** number exactly as displayed.
4. Follow the instructions that Xerox DocuShare or your DocuShare reseller provided to obtain a site license string.
5. When you have the license string, return to the **Site Management | License page** and enter the string in the **License** field. Do not use your old site license nor a trial license.

Post upgrade tasks

1. Reset user levels for all user accounts on your site. If you upgraded from DocuShare 5.x, all user accounts are now set to the CPX level. You must now activate and set each account to either Read-Only or DocuShare user levels as appropriate.

Refer to the *DocuShare Administrator Guide* for information on user levels and changing user levels through **Account Management | Users | Change User Level**.
2. Run database optimization as defined in the *DocuShare Administrator Guide* database optimization procedures.

3. To access customized VDF and image files, the upgrade installer relocates these files to <DSHome>/DSUpgrade/BackUpDir.0/amber.jar and <DSHome>/DSUpgrade/BackUpDir.0/root.jar.

Note: VDF files customized to work with DocuShare 5.x or older are not upgraded by the installer and do not work with this release of DocuShare. Refer to the DocuShare VDF Reference Guide to migrate your custom VDFs to the current DocuShare release.

4. If you changed the Subscription Notification settings to clear the event queue, go to the **Services and Components | Subscription** administration page and return the Weekly Notification Day, Hour, and Minute to their values prior to the upgrade.
5. Go to **Site Management | Access Policies**.
6. Return the **Site Access Authority** to the pre-upgrade setting, then click **Apply**.

Update DocuShare software or add a language

Patches, updates, and additional languages for DocuShare software, when available, are easily installed using the DocuShare update wizard.

- Before you install software updates, make sure the selected update is compatible with your version of DocuShare. Go to **About DocuShare**, on your site home page or in the Administration Menu, to locate your version number.
- If documentation is supplied with an update, read the documentation before starting the installation.

Install a software update

1. Log into the server as a UNIX server administrator (root).
2. In a terminal window, cd to **<DSHome>/bin** and enter **./stop_docushare.sh -q** to stop the DocuShare server.
3. Download, or copy, the software to a temporary directory on your server and unzip and extract the package.
4. In the software directory, open the Solaris directory.
5. In the Solaris directory, open the DocuShare directory and double-click **dsUpdate** to start the update installation Wizard. If you work from a command prompt window, cd to the DocuShare directory and run **./dsUpdate.sh -console** to start the installation.
Be patient; it takes several minutes before the system displays the first install Wizard screen.
6. Once the install Wizard begins, follow the onscreen instructions. Click **Next** to proceed or click **Back** to return to a previous screen.
7. When asked to select an update, check the appropriate update, or browse to the location of the update **jar** file, click **Add Update**, then click **Next** to start the installation.
8. When the installation successfully completes, click **Finish** to close the installer.
9. In a terminal window, cd to **<DSHome>/bin**, then enter **./start_docushare.sh** to start DocuShare, or **start_docushare.sh console** to see the log to the console.
10. Use a browser to connect to your site, and log in as an administrator.
11. If your specific update requires a new license, obtain a site license string and apply it to the **License** field on the **Site Management | License** page.

Install a language

1. Log into the server as a UNIX server administrator (root).
2. In a command prompt window, cd to **<DSHome>/bin** and enter **./dsservice.sh -shutdown DocuShare** to stop the server.
3. In the Solaris directory, open the DocuShare directory and double-click **dsUpdate** to start the update installation Wizard. If you work from a command prompt window, cd to the DocuShare directory and run **./dsUpdate -console** to start the installation.

4. When asked to select a language, check the appropriate language, and then click **Next** to start the installation.
5. When the installation successfully completes, click **Finish** to close the update installer.
6. Restart DocuShare.
7. Go to **Site Management | Installed Languages** to make any changes in your default and installed language choices.

DocuShare on a Linux platform

Installation logs

The DocuShare installer records all initial installation activity and stores it in **InstallLog.txt** in the /tmp directory of your server. After the installer has created the DocuShare directory, it creates a second **DocuShareInstallLog.txt** file in the home directory; where it stores the remaining installation information.

To save the initial InstallLog file, start the installation process in a command prompt window by entering the command: **./docushare -P docushareLog.cleanUp=false**.

Install DocuShare

Before you begin

1. Inspect your operating system for, and install if missing, the following Linux software libraries:
 - glibc.i686
 - libXau.i686
 - libxcb.i686
 - libX11.i686
 - libXext.i686
 - libXi.i686
 - libXtst.i686
 - libXp.i686
 - libXp.x86_64
 - libXmu.i686
 - libXpm.i686
 - glib2.i686
 - pam.i686
 - glibc-devel.i686
 - libXrender.i686

- freetype.i686
 - expat.i686
 - fontconfig.i686
 - libXft.i686
 - elfutils-libs.i686
2. Review Chapter 1 of this guide to make sure your server meets the minimum requirements for DocuShare installation and that you have gathered the information required by the install Wizard.
 3. If you have chosen not to install the DocuShare supplied web server, make sure you have installed and configured the web server of your choice, and that web server is running before you begin DocuShare installation.
 4. If you have chosen not to install the DocuShare supplied database, make sure you have installed and configured the database of your choice, and that database is running before you begin DocuShare installation.
 5. For an easier installation, we recommend that you install DocuShare on a clean server; one with newly installed operating system software.
 6. If you have other instances of DocuShare running on the same server, make sure those instances are running before installing additional instances. Failure to do so can later result in indexing problems and in situations where stopping one instance of DocuShare stops all instances.

Start the installation



Caution

If you have other instances of DocuShare running on the same server, make sure those instances are running before installing additional instances.

1. Log into the server as a UNIX server administrator (root).
2. Download the DocuShare software file to a temporary directory on your server and extract the tar file.
3. In a command prompt window go to **<DSHome>/<Linux>/DocuShare** and enter **docushare**.

Be patient; it takes several minutes before the system displays the first install Wizard screen.
4. Follow the onscreen instructions; accept the defaults or enter your own configuration information.
5. Click **Next** to advance the installation or click **Back** to return to a previous page to make a change.

Before the installer loads DocuShare, the Wizard allows you to make changes to your choices. After installation, the administrator of the site has the authority to change most of the information that was provided during installation; using either the Admin UI or a command prompt window.
6. In the database configuration window, select a database option then click **Next** and enter the configuration information for your database.

If you selected Oracle 12c, add **c##** to the beginning of the user name in the **Database User** field. For example; **c##lq661b110**.

If you selected PostgreSQL, enter the Database User Password and select **Create Database**.

7. In the Web Server Interaction window, select **Tomcat only**.
8. In the UNIX Account Parameters window, enter the appropriate information.

The default is **nobody**, which allows any user with an UNIX account to login and start DocuShare.

If you installed scan to DocuShare, you must be logged in as root to start DocuShare and to enable the scan feature. For non-root users to enable the scan to DocuShare feature, the FTP server default port (port 21) must be changed to another port that is above port 1024 (ftpd.conf) and the Xerox Work Centres used for scanning must be able to specify this port.

Finish the installation

1. When the installation successfully completes, click **Finish** to close the installer.
2. Set your UNIX virtual display buffer to operate within an X Windows system.

DocuShare operates in an X Windows environment; set the display buffer to use all of the DocuShare features. In a headless system, an error occurs if the display buffer is not correctly set.
3. In a command prompt window, cd to **<DSHome>/bin**, then enter **./start_docushare.sh** to start DocuShare.

At initial startup, DocuShare automatically updates the search indexes. Wait five minutes before you access the site with a browser.

Note: To prevent the Search Service from stopping when you exit the shell, use either the **start_docushare.sh bg** or the **start_docushare.sh bg &** command to start DocuShare in background mode.

4. If you installed **Scan-to-DocuShare via FTP**, disable the UNIX FTP service on your UNIX system.

Note: If Scan-via-FTP is installed, you must be root to start DocuShare to enable the scan feature. To enable the Scan-via-FTP feature by non-root users, the FTP server default port (port 21) must be modified to another port above port 1024 (ftpd.conf) and the Xerox Work Centres must be able to specify this port.

- a. Log into the server as a UNIX server administrator (root).
- b. From the Start menu, select **Service Configuration**.
- c. In the Service Configuration window, de-select **wu-ftp**.

License the site

1. Use a browser to connect to your newly installed site.
 - The default URL is **http://<fully qualified DNS name>:8080/docushare**.
 - If DocuShare was installed in the home directory on your web site, the URL is: **http://<fully qualified DNS name>:<port>/**
 - If DocuShare was installed in a subdirectory on your web site, the URL is: **http://<fully qualified DNS name>:<port>/<subdirectory_path>/**

- If you installed Apache on your server, then the :<port> component of the URL is not used. For example: http://<fully qualified DNS name>/docushare
 - If you installed only Tomcat on your server, then the :<port> component of the URL is 8080 (default).
2. Use the admin password you set during installation and log into the site as *admin*.
 3. On the navigation bar, click **Admin Home**.
 4. From the Administration menu, click **Site Management | License**.
 5. On the License page, locate and write down the **Host ID** exactly as displayed.
 6. Follow the instructions that Xerox DocuShare or your DocuShare reseller provided to obtain a site license string.
 7. When you have the license string, return to the **Site Management | License page** and enter the string in the **License** field.
 8. Refer to the *Administrator Guide* for information on post-installation site configuration, such as setting up your site to use SSL.

Uninstall DocuShare

Uninstall does not remove the DocuShare directory that includes your DocuShare repository content. To be safe, before uninstalling DocuShare move the repository content to another storage media by using the DocuShare command line utility, **dsexport**. Refer to the *DocuShare Command Line Utilities Guide* for details.

Uninstall removes all installed language packs.



Caution

The DocuShare uninstaller only removes DocuShare, not the installed database. You should backup data for all Linux applications sharing the database.

To uninstall DocuShare:

1. Log into the server as a UNIX server administrator (root).
2. Stop the DocuShare server by doing the following:
 - a. Open a command prompt window
 - b. Change the directory to **<DSHome>/bin**
 - c. Enter **./stop_docushare.sh**
3. Change the directory to **<DSHome>/_uninst**.
4. Enter **./doc_uninstall**, then follow the onscreen instructions.
5. After doc_uninstall uninstalls DocuShare, manually delete the directory where DocuShare was installed.

Upgrade DocuShare

If you are upgrading from DocuShare 6.5.3 or earlier, upgrade to DocuShare 6.6.1 R2 before upgrading to DocuShare 7. If you are upgrading from DocuShare 6.6.1, upgrade to DocuShare 6.6.1 Update 2 before upgrading to DocuShare 7. If you are upgrading from DocuShare 6.6.1 R2 or 6.6.1 Update 2 or later, you can upgrade directly to DocuShare 7.

A DocuShare upgrade utility is included with the software install Wizard. The utility can take sites as low as version 5.0.3 and upgrade them to the current version of DocuShare.

System requirements review

Before making any DocuShare upgrades, review the system requirements for the upgrade version, and make sure your server meets those requirements. Look carefully at the operating system, database, web server, memory and disk space requirements for the upgrade.

Installation logs

The DocuShare installer records all upgrade activity and stores it in the DocuShareInstallLog.txt file.

Before you start the upgrade procedure

- A day prior to upgrading the site, inform users that the site will be down
 - a. Go to **Site Management | Site Operations**.
 - b. In the **Admin Message** field, enter a message telling users when the site will be unavailable and for how long; then select **Yes** in the **Show Admin Message** field.
 - c. Click **Apply**.
- Review the information required for DocuShare software installation presented in Chapter 1. Record all of your current configuration settings so you can enter them in the upgrade Wizard windows.
- From the Administration menu, click **Site Management | License**. On the **License** page, locate and write down the **Host ID** number of the server.
- Stop all automated or programmatically generated activities; especially those that use the Content Intake Manager, Content Rules, or Scan to DocuShare services.
- Close site access
 - a. Log into the DocuShare site as *admin*.
 - b. Go to **Site Management | Access Policies**.
 - c. Set the **Site Access Authority** to Administrator, then click **Apply**.
 - d. Go to **Site Management | Site Operations**.
 - e. In the **Admin Message** field, enter a message telling users that the site is going down in ten minutes, select **Yes** in the **Show Admin Message** field, then click **Apply**.
 - f. After ten minutes, enter the message *DocuShare is currently in read-only mode* in the **Admin Message** field.

- g. In the **System Mode** field, select **Read Only**.
- h. In the **Show Admin Message** field select **Yes**.
- i. Click **Apply**.
- Backup the IDOL database
 - a. Make sure the target directory exists and is empty before starting backup. The target directory is represented as <exportdir> in the command.
 - b. Run the command **idoltool.sh -s export <exportdir>**.
- Clear the event queue
 - a. Go to **Site Management | Site Operations**.
 - b. In the **System Mode** field, select **Read Write** and select **No** in the **Show Admin Message** field; then click **Apply**.
 - c. Go to **Services and Components | Subscription**.
 - d. Set the **Weekly Notification Day** to the current day of the week, and set the **Weekly Notification Hour** and **Weekly Notification Minute** to five minutes from the current time; then click **Apply**.
 - e. Wait ten minutes before proceeding with the upgrade.

This allows the DocuShare notification service to send all subscribed notifications and clear the event queue. Failure to clear the event queue before starting the upgrade results in the lost of all events waiting in the queue.
- Stop DocuShare
 - a. Log into the server as a UNIX server administrator (root).
 - b. In a command prompt window, cd to <DSHome>/bin and enter **./dsservice.sh -shutdown DocuShare** to stop the server.
- Backup the site database
 - a. In your database server manager, stop the database.
 - b. Perform a system backup of your DocuShare site.
 - c. When the backup is finished, start the database. The database must be running for the DocuShare Installer to upgrade the database schema.
 - d. If you are using a Microsoft SQL Server database, run **exec sp_fulltext_database enable** on the server to enable full text search.

Start the upgrade

To have DocuShare save all configuration and upgrade data, start the upgrade in a Command Prompt window by entering the command line: **docushare -P docushareLog.cleanUp=false**

1. Log into the server as a UNIX server administrator (root).
2. Download, or copy, the software to a temporary directory on your server and extract the tar file.
3. In a command prompt window go to <DSHome>/<Linux>/DocuShare and enter docushare.
4. When the Upgrade Option window appears, select **Upgrade**.

Be patient; it takes several minutes for the system to load and start the installer.

5. Follow the onscreen instructions; accept the defaults or enter your own configuration information.

Finish the upgrade

1. When the upgrade successfully completes, click **Finish** to close the installer.
2. Set your UNIX virtual display buffer to operate within an X Windows system.

DocuShare operates in an X Windows environment; set the display buffer to use all of the DocuShare features. In a headless system, an error occurs if the display buffer is not correctly set.
3. In a command prompt window, cd to **<DSHome>/bin**, then enter **./start_docushare.sh** to start DocuShare.

At initial startup, DocuShare automatically updates the search indexes. Wait five minutes before you access the site with a browser.

Note: To prevent the Search Service from stopping when you exit the shell, use either the **start_docushare.sh bg** or the **start_docushare.sh bg &** command to start DocuShare in background mode.

4. If you installed **Scan-to-DocuShare via FTP**, disable the UNIX FTP service on your UNIX system.

Note: If Scan-via-FTP is installed, you must be root to start DocuShare to enable the scan feature. To enable the Scan-via-FTP feature by non-root users, the FTP server default port (port 21) must be modified to another port above port 1024 (ftpd.conf) and the Xerox Work Centres must be able to specify this port.

- a. Log into the server as a UNIX server administrator (root).
 - b. From the Start menu, select **Service Configuration**.
 - c. In the Service Configuration window, de-select **wu-ftp**.
5. If your DocuShare site uses LDAP over a secure SSL channel, you need to import the SSL certificate into the newly installed **dsstrust** store. Instructions for importing the LDAP SSL Certificate are in the *LDAP Active Directory Guide* that is located on the Help page of your DocuShare server.

License the site

1. Use a browser to connect to your newly installed site and login as *admin*.
2. From the Administration menu, click **Site Management | License**.
3. On the License page, locate and write down the **Host ID** number exactly as displayed.
4. Follow the instructions that Xerox DocuShare or your DocuShare reseller provided to obtain a site license string.
5. When you have the license string, return to the **Site Management | License page** and enter the string in the **License** field. Do not use your old site license nor a trial license.

Post upgrade tasks

1. Reset user levels for all user accounts on your site. If you upgraded from DocuShare 5.x, all user accounts are now set to the CPX level. You must now activate and set each account to either Read-Only or DocuShare user levels as appropriate.

Refer to the *DocuShare Administrator Guide* for information on user levels and changing user levels through **Account Management | Users | Change User Level**.

2. Run database optimization as defined in the *DocuShare Administrator Guide* database optimization procedures.
3. To access customized VDF and image files, the upgrade installer relocates these files to <DSHome>/DSUpgrade/BackUpDir.0/amber.jar and <DSHome>/DSUpgrade/BackUpDir.0/root.jar.

Note: VDF files customized to work with DocuShare 5.x or older are not upgraded by the installer and do not work with this release of DocuShare. Refer to the DocuShare VDF Reference Guide to migrate your custom VDFs to the current DocuShare release.

4. If you changed the Subscription Notification settings to clear the event queue, go to the **Services and Components | Subscription** administration page and return the **Weekly Notification Day, Hour, and Minute** to their values prior to the upgrade.
5. Go to **Site Management | Access Policies**.
6. Return the **Site Access Authority** to the pre-upgrade setting, then click **Apply**.

Update DocuShare software or add a language

Patches, updates, and additional languages for DocuShare software, when available, are easily installed using the DocuShare update wizard.

- Before you install software updates, make sure the selected update is compatible with your version of DocuShare. Go to **About DocuShare**, on your site home page or in the Administration Menu, to locate your version number.
- If documentation is supplied with an update, read the documentation before starting the installation.

Install a software update

1. Log into the server as a UNIX server administrator (root).
2. In a terminal window, cd to **<DSHome>/bin** and enter **./stop_docushare.sh -q** to stop the DocuShare server.
3. Download, or copy, the software to a temporary directory on your server and extract the package.
4. In the software directory, open the Linux directory.
5. In the Linux directory, open the DocuShare directory and double-click **dsUpdate** to start the update installation Wizard. If you work from a command prompt window, cd to the DocuShare directory and run **./dsUpdate.sh -console** to start the installation.

Be patient; it takes several minutes before the system displays the first install Wizard screen.

6. Once the install Wizard begins, follow the onscreen instructions. Click **Next** to proceed or click **Back** to return to a previous screen.
7. When asked to select an update, check the appropriate update, or browse to the location of the update **jar** file, click **Add Update**, then click **Next** to start the installation.
8. When the installation successfully completes, click **Finish** to close the installer.
9. In a terminal window, cd to **<DSHome>/bin**, then enter **./start_docushare.sh** to start DocuShare or **start_docushare.sh console** to see the log to the console.
10. Use a browser to connect to your site, and log in as an administrator.
11. If your specific update requires a new license, obtain a site license string and apply it to the **License** field on the **Site Management | License** page.

Install a language

1. Log into the server as a UNIX server administrator (root).
2. In a command prompt window, cd to **<DSHome>/bin** and enter **./dsservice.sh -shutdown DocuShare** to stop the server.
3. In the Linux directory, open the DocuShare directory and double-click **dsUpdate** to start the update installation Wizard. If you work from a command prompt window, cd to the DocuShare directory and run **./dsUpdate -console** to start the installation.

4. When asked to select a language, check the appropriate language, and then click **Next** to start the installation.
5. When the installation successfully completes, click **Finish** to close the update installer.
6. Restart DocuShare.
7. Go to **Site Management | Installed Languages** to make any changes in your default and installed language choices.

Database configuration



Caution

In many instances, correct installation and configuration of a database requires the expertise of a qualified database administrator.

Oracle

On the Oracle side

Before starting the DocuShare software installation, the Oracle database administrator must:

- Create a DocuShare/Oracle user and a tablespace.

If you choose to use an existing Oracle database or prefer to manually create and define an Oracle tablespace, the following is an example of a typical DocuShare tablespace creation script.

```
CREATE TABLESPACE <name> DATAFILE <file> SIZE <size> AUTO EXTEND ON
NEXT 512K MAXSIZE UNLIMITED EXTENT MANAGEMENT LOCAL AUTOALLOCATE;
```

- Designate a location on the Oracle system that has the required space for the new tablespace file.
- Set character encoding to AL32UTF8 if the system will be operating with multibyte characters.
- Change the value of `nls_length_semantics` from `byte` to `char` if the system will be operating with multibyte characters. If the value of `nls_length_semantics` is `byte`, the max length of DocuShare is different from the max length of DB because 1 multi-byte character in UTF-8 is 3byte.

Connect role

DocuShare 5.x had a Connect role that gave the DocuShare user account the authority to create Oracle connections, table, and sequence privileges. If upgrading from DocuShare 5.x to DocuShare 6, an additional role, CTXAPP, must be granted to Oracle database users. CTXAPP is required by the DocuShare Extensible Database Service (XDB). DocuShare 6 installation automatically grants both Connect and CTXAPP roles to the DocuShare user account.

The database administrator can grant the CTXAPP role to DocuShare users by logging on as either SYSTEM or as a user with DBA privileges and entering:

```
SQL> GRANT CTXAPP, CREATE SEQUENCE to <DS user>.
```


For Oracle 10.2.0.4, the Connect role has been stripped of the create table and create sequence privileges. These privileges need to be restored. If an Oracle 9.x or 10.1 database is upgraded to 10.2.0.4, the database administrator needs to make sure that the following roles are present:

- Connect
- Create table
- Create Sequence
- CTXAPP

Grant all of these roles simultaneously by entering:

```
SQL> GRANT Connect, Create Table, Create Sequence, CTXAPP to <DS
User>;
```

On the DocuShare side

To configure DocuShare to work with Oracle, the install Wizard requires a valid Oracle system account or an account with DBA privileges. The install Wizard uses the Oracle system account to create a new DocuShare/Oracle user account and to designate the new tablespace as the default for the new DocuShare/Oracle account.

When creating the database connection, the install Wizard works in the following order.

1. Creates a new Oracle user account for DocuShare.
2. Creates a new default tablespace for the new Oracle user account.
3. Creates DocuShare tables.
4. Populates the tables with initial data.

If for any reason a step fails, the Wizard stops the installation. Common reasons for stopping the installation include the user account and tablespace the install Wizard creates already exist.

Fields in the install Wizard Oracle database page:

- **Database User** — the account that DocuShare uses to log into the database. DocuShare supports auto-create Oracle user. If the site uses Oracle 12c, add c## to the beginning of the user name in this field. For example; c##lq661b110.
- **Database User Password** — the password for the Database User account
- **Database Port** — the port that DocuShare uses to connect to the database
- **Tablespace Name** — the name of the tablespace where the database stores all DocuShare data
- **Indexspace Name** — the name of the tablespace where the database stores all DocuShare indices
- **Database SID** — the unique name of the Oracle database instance
- **Database Host Name** — the name of the database server
- **Create Tablespaces** — select if tablespace entered in the Tablespace Name field has not been created, and you want the Wizard to create the tablespace for you

- **Create User** — select if the user name entered in the Database User field has not been created, and you want the Wizard to create the user account for you

SQL Server

On the SQL Server side

Before starting the DocuShare software installation, make sure of the following:

- If you install the database on the same server as you install your DocuShare site, set the maximum memory use to 50 % of the physical RAM of the server.

On the DocuShare side

Fields in the install Wizard SQL Server database page:

- **Database User** — the account that DocuShare uses to log into the database
- **Database User Password** — the password for the Database User account
- **Database Port** — the port that DocuShare uses to connect to the database
- **Database Name** — the name of the database used to store DocuShare data
- **Database Host Name** — the name of the database server
- **Database Instance Name** — the name of the database instance that you want DocuShare to use
- **Use Database Default Instance** — select if you want to use the default database instance and leave the Database Instance Name field blank
- **Use Database Named Instance** — select if you want to use a named database instance and enter that name in the Database Instance Name field
- **Create Database** — select if a database has not been created and you want the Wizard to create the database for you

PostgreSQL

Windows platform

On the PostgreSQL side

Before starting the DocuShare software installation, the PostgreSQL database administrator must do the following:

- Create a DocuShare/PostgreSQL tablespace by logging into the database server as postgres, and running the command **createdb -E UNICODE <DocuShare Database Name>**. Give the tablespace a unique name.
- Enable TCP/IP connectivity, unless it was enabled during database software installation.

On the DocuShare side

Note: The install Wizard creates the system user account for the database. If you already have a system user account for PostgreSQL, do not use it for the DocuShare installation. Use the account that the Wizard creates.

To configure DocuShare to work with PostgreSQL, the install Wizard requires the following information:

- **Database User** — the account that DocuShare uses to log into the database
- **Database User Password** — the password for the Database User account
- **Database Port** — the port that DocuShare uses to connect to the database
- **Tablespace Name** — the name of the tablespace where the database stores all DocuShare data
- **Database Host Name** — the name of the database server
- **Create Database** — select if a database has not been created and you want the Wizard to create the database for you

Solaris platform

On the PostgreSQL side

Before starting the DocuShare software installation, the PostgreSQL database administrator must do the following:

- Create a DocuShare/PostgreSQL tablespace by logging into the database server as postgres, and running the command **createdb -E UNICODE <DocuShare Database Name>**. Give the tablespace a unique name.
- Enable TCP/IP connectivity, unless it was enabled during database software installation.

On the DocuShare side

Note: The install Wizard creates the system user account for the database. If you already have a system user account for PostgreSQL, do not use it for the DocuShare installation. Use the account that the Wizard creates.

To configure DocuShare to work with PostgreSQL, the install Wizard requires the following information:

- **Database User** — the account that DocuShare uses to log into the database
- **Database User Password** — the password for the Database User account
- **Database Port** — the port that DocuShare uses to connect to the database
- **Tablespace Name** — the name of the tablespace where the database stores all DocuShare data
- **Database Host Name** — the name of the database server
- **Create Database** — select if a database has not been created and you want the Wizard to create the database for you

Linux platform

On the PostgreSQL side

Before starting the DocuShare installation, the PostgreSQL database administrator must do the following:

- Create a DocuShare/PostgreSQL tablespace by logging into the database server as postgres, and running the command **createdb -E UNICODE <DocuShare Database Name>**. Give the tablespace a unique name.
- Enable TCP/IP connectivity, unless it was enabled during database software installation.

On the DocuShare side

Note: The install Wizard creates the system user account for the database. If you already have a system user account for PostgreSQL, do not use it for the DocuShare installation. Use the account that the Wizard creates.

To configure DocuShare to work with PostgreSQL, the install Wizard requires the following information:

- **Database User** — the account that DocuShare uses to log into the database
- **Database User Password** — the password for the Database User account
- **Database Port** — the port that DocuShare uses to connect to the database
- **Tablespace Name** — the name of the tablespace where the database stores all DocuShare data
- **Database Host Name** — the name of the database server
- **Create Database** — select if a database has not been created and you want the Wizard to create the database for you

Web server bridge

Create a bridge to an Apache web server

If you choose to use an Apache web server, you must manually create the bridge between the web server and the DocuShare Tomcat servlet.

During DocuShare software installation, the Wizard installs the following Apache files:

- <DSHome>/tomcat/bin/native/apacheX.X/mod_jk.so
- <DSHome>/tomcat/conf/jk/apacheX.X/httpd.conf

To manually create a bridge between an Apache web server and the DocuShare Tomcat servlet:

1. In your DocuShare directory, open the file
<DSHome>/tomcat/conf/jk/apacheX.X/httpd.conf.
2. Copy all of the lines of code that appear in this file.
3. Locate the directory where you installed your Apache software, open the httpd.conf file in that directory, and paste the lines of code into that file.
4. Save the file.
5. Restart Apache.

Create a bridge to an IIS web server

If, during DocuShare installation, you choose Tomcat only but later decided to use IIS as your web server, you can run the DocuShare IIS Software Bridge Management Tool to create a bridge to IIS.

The IIS Software Bridge Management Tool installs the bridge dll and plugs it into the IIS software. When IIS restarts, the bridge dll loads into IIS memory. As the dll loads into memory, it accesses registry key (HKEY_LOCAL_MACHINE\Software\Apache Software Foundation) to configure runtime settings.

The settings include the logging level, log file locations, the workers.properties file, and the uriworkemap.properties file.

The workers.properties file defines the location of the ajp13 protocol, which in this case would be Tomcat. The uriworkemap.properties file defines the URLs that IIS delegates to the bridge. The install Wizard updates these files to allow the dll to function. Information about more extensive URL mapping or more complicated IIS settings, such as configuring for multiple DocuShare sites, is available on the Apache web site.

There is no need to uninstall your current IIS bridge setup; the Wizard overwrites current settings at <http://tomcat.apache.org/connectors-doc/>.

To use the IIS Tool to create a bridge to an IIS web server:

1. Download the DocuShare IIS Tool software to a temporary directory on your server, and then unzip the file.
2. Navigate to the \Windows\IIS directory and double-click iistool.exe.
This starts the DocuShare IIS Bridge Management Tool Wizard.
3. In the next displayed window, select a location for the bridge installation; then click **Next**.
4. Enter the appropriate IIS bridge values in the displayed fields.
This includes the Tomcat Bridge Port Number, the IIS Port Number, the DocuShare Root, and the Host DNS Name. Generally, you do not need to change the default values.
5. Click **Next**.
The tool installs the bridge to the IIS web server.
6. When the Wizard completes installation, click **Finished** to close the window.
The Wizard restarts IIS.

Note: If you have a problem installing the bridge software, use iistool.exe and install the software to the C:\program files directory.

File upload problems using IIS with the DocuShare desktop applications

When using IIS with Windows Server 2008 SP2 or R2 you may have problems using the DocuShare desktop applications to upload files larger than 28.6 MB. This is due to an IIS 7.x file size limitation default setting. To increase the file upload size setting, refer to the IIS documentation and to the Microsoft website for the most current information on changing the IIS request filtering feature settings and request limits.

If you have access to the DocuShare Knowledge Base, refer to <http://customer.docushare.xerox.com/s.nl/ctype.KB/it.I/id.46685/KB.193/f?category=3> for a knowledge base article about this problem.

Add-on installation

OCR (Optical Character Recognition)

- Obtain a new DocuShare site license that includes OCR. Installing software alone will not enable OCR.
- Verify that your server meets the minimum system requirements as are listed on the DocuShare OCR software download page.
- Your DocuShare server must have more than one processor and running .NET 3.5 or higher.

Installing OCR software

1. From your site **Help Desk**, select **Downloads**, then select **Software Extras for the DocuShare Platform**; this takes you to an external web site.
2. On the web site, select **Optional Add-on for DocuShare CPX** and then select the **Optical Character Recognition** download.
3. Download the OCR software package to a temporary directory on your DocuShare server.
4. Unzip the OCR software package to a new folder, in the temporary directory, named OCR.
5. Log into the DocuShare server as a Windows administrator.
6. In the Windows Administrator Tool, select and open the Services application, select **DocuShare** and stop the service.
7. In the unzipped OCR software directory, open the Win32 directory.
8. In the Win32 directory, open the DocuShare directory and double-click dsUpdate.exe to start the OCR installation Wizard.

Be patient; it takes a few minutes to load and start the installer.
9. Once the install Wizard begins, follow the onscreen instructions. Click **Next** to proceed or **Back** to return to a previous screen.
10. When asked, check the **OCR Update**, browse to and select the **ocr.jar** file, then click **OK**.
11. Click **Add Update**, then click **Next**.
12. When the installation successfully completes, click **Finish** to close the installer.
13. In the Windows Administrator Tool, select and open the Services application, select **DocuShare** and **start** the service.
14. Use a browser to connect to your site, and log in as an administrator.
15. Go to **Site Management | License** and enter your new license string.
16. Refer to the *DocuShare OCR Guide* for instructions on how to use OCR to convert scanned images into searchable document formats.

Additional languages for OCR

The OCR feature uses the default language of the installed DocuShare site. To use additional languages for OCR, you must have the language packs installed on the site and you must configure the `OCR_converter.xml` file to accept new languages.

To add languages for OCR:

1. In the DocuShare installation directory, go to **/config** and open the **Converters.xml** file.
2. Near the bottom of the open Converters xml file, locate the line **<language/>**.
3. Edit the line to include the desired languages.
For example; `<language/>en,fr,de</language>`
4. Save and close the file.

Xerox ConnectKey for DocuShare

ConnectKey is installed automatically with DocuShare 7 installation. There is no install/uninstall option built into the DocuShare install wizard.

To uninstall or to install ConnectKey:

1. Contact DocuShare Customer Support, and request the ConnectKey for DocuShare installer file for DocuShare 7.
2. Download and unzip the file to a directory on your DocuShare server.
3. Stop DocuShare.
4. In the extracted file, click **dsInstall.exe**
5. In the displayed wizard window, select either to **uninstall** or to **install** ConnectKey for DocuShare.
6. When finished, restart DocuShare.

Archive Server

Installing Archive Server software is almost identical to installing standard DocuShare software. The only difference is the type of software installation you select; in this case DocuShare Archive Server.

Refer to Chapter 1 of this guide to verify the system requirements and to make sure you have the information required by the install Wizard. System requirements for an Archive Server are the same as those for a standard DocuShare site.

After you have installed the DocuShare Archive Server software, send a license request email to your DocuShare License Administrator or your DocuShare reseller or distributor. When your account is verified, you will be emailed a license string.

Install the Archive Server

1. Depending on the platform you are using, refer to that chapter of this guide.
2. Following the Install DocuShare instructions exactly as though you were installing a standard DocuShare site, but when the install Wizard displays the window asking you for the type of installation you want; select **DocuShare Archive Server**.

Note: The Archive Server must have the same domain name as the DocuShare sites that use the Archive Server.

3. When the installation successfully completes and you have started the service, use a browser to connect to the Archive Server.
4. Follow the standard DocuShare site license procedure to license the Archive Server. Make sure you use the license string that enables Archive Server. Installing software alone does not enable the Archive Server.
5. After licensing, reboot the server.

Configure client sites to use the Archive Server

1. To configure any DocuShare site to use the Archive Server, go to Services and Components | Archive Server of the Admin UI of that site.
2. On the Archive Server page, enter the hostname and port number of the Archive Server. Enter that information in the connection test field to make sure the DocuShare site can connect to the Archive Server.
3. You can also use the Archive Server page to set how often the site polls for documents marked for archiving.

Uninstall the Archive Server

1. Depending on the platform you are using, refer to that chapter of this guide.
2. Follow the Uninstall DocuShare instructions exactly as though you were uninstalling a standard DocuShare site.

Document Viewer

The Document Viewer add-on integrates a viewer within the Web UI that provides search, annotation, and redaction features. DocuShare uses the Accusoft PrizmDoc Server for the Document Viewer add-on.

This add-on is in English only.

System requirements

DocuShare server

- Linux and Windows only

PrizmDoc server

- Minimum of 6 CPU cores
- Minimum of 16 GB RAM
- Minimum of 100 GB of free disk space

Windows operating systems supported

- Windows Server 2008 R2 SP1 (64 bit)
- Windows Server 2012
- Windows Server 2012 R2
- Windows 7 (64 bit)
- Windows 8 (64 bit)
- Windows 10 (64 bit)

Linux operating systems supported

- CentOS 5.9+, 6.4+, 7 (64 bit)

Note: Assistance from Xerox Professional Services may be required for installation on the following supported Linux platforms:

- Debian 7.1 (Wheezy) (64 bit)
- Red Hat Enterprise Linux 5.9+, 6.4+, 7 (64 bit)
- Ubuntu 12.04 LTS, 13.04 (64 bit), 14.04 LTS (64 bit)

Steps for the Document Viewer installation

1. Install the PrizmDoc Server software
2. Install the Document Viewer hotfix
3. Install the Document Viewer add-on

1 - Install the PrizmDoc Server software

The PrizmDoc server must be installed prior to installing the Document Viewer hotfix and add-on.

Installation on a Windows server

1. Create a local administrator account on the server that you will use to host the document viewer service.
- Note:** Install the PrizmDoc Server software on a server other than the one you will use to run DocuShare.
2. On that server, open a command prompt by selecting **Run as Administrator**.
 3. Enter and run the following command:
**Start PrizmDocServer.exe ServiceUser=<serverName>\PrizmUser
ServicePassword=<password> InstallFolder=<installDir> -s -l output.log**
 4. After the PrizmDoc Server software is installed, license the viewer by running **<installDir>\plu\plu.exe**; then select **I have purchased a license**, select **OEM**, and enter the required information.
 5. After licensing the PrizmDoc Server software, go the Windows Services page and start the Prizm service.
 6. Verify the installation by going to **http://localhost:18681/admin**.

Installation on a Linux server

1. Verify that either LibreOffice or OpenOffice have been installed on your DocuShare server. If neither are installed, in a command window run **yum install cairo** to install the Cairo library.
2. Uncompress the Centos RPM Package Manager into a directory on the server.
3. In a terminal window, navigate to the directory you used in Step 2.
4. As root, run the command **yum install -y --nogpgcheck *.rpm**.
5. Navigate to **/usr/share/prizm**, and run the command **setup.sh**.
6. For **install type**, answer with **deploy**.
7. For the next **install type**, answer **OEM**.
8. For **license path**, enter the path to the license file that is located on your server.
9. Wait for the setup to complete; it will then start the document viewer server.
10. Verify the installation by going to **http://localhost:18681/admin**.
11. Install the Microsoft core fonts from **wget http://www.itzgeek.com/msttcore-fonts-2.0-3.noarch.rpm rpm -Uvh msttcore-fonts-2.0-3.noarch.rpm**.

These fonts are required when burning-in annotations and redactions.

When configuring the PrizmDoc Server, note the following parameters and values. You will need them later when installing the Document Viewer add-on.

PrizmDoc Configuration Field Name	Value
Service User	PrizmDoc service user name. Required if running on a Windows server; ignore if running on Linux.
Service User Password	Password for the PrizmDoc service user. Required if running on a Windows server; ignore if running on Linux.
Document Viewer Installation Folder	The absolute path to the PrizmDoc install folder. Required if running on a Windows server; ignore if running on Linux.
PrizmDoc Server Host	Path to the server hosting the PrizmDoc Server software.
PrizmDoc Server Port	The port used by the PrizmDoc Server.
PrizmDoc Server Protocol	The protocol can be either HTTP or HTTPS.

2 - Install the Document Viewer hotfix

Install the DocuShare 7.0 Update 1 Hotfix 24 (**ds700update1hf24**) on your DocuShare server.

Refer to either Windows [Install a software update](#) on page 26 or Linux [Install a software update](#) on page 46.

3 - Install the Document Viewer add-on

Installation on a Windows server

1. Log into your DocuShare server as a Windows administrator.
2. In a command prompt window, go to **<DSHome>/bin** and enter **stop_docushare.bat -q**.
3. Download, or copy, the DocuShare 7 Document Viewer add-on software to a temporary folder on your server, and decompress the file.
4. Open the folder, then locate and double-click **dsInstall**. Be patient; it takes several minutes before the system displays the first install Wizard screen.
5. Once the install Wizard begins, follow the onscreen instructions. Click **Next** to proceed or click **Back** to return to a previous screen.
6. When asked to select an update, check the appropriate add-on by selecting **Install DocuShare Document Viewer**, then click **Next** to start the installation.
7. In the **PrizmDoc Config** window, enter the corresponding values in the displayed fields (refer to table above), and then click **Confirm**.
8. When the installation successfully completes, click **Finish** to close the installer.
9. In a command prompt window, go to **<DSHome>/bin** and enter **start_docushare.bat** to start DocuShare, or enter **start_docushare.bat console** to view the log on the console.

10. Use a browser to connect to your site, and log in as an Administrator.
11. Obtain a new site license string that includes the Document Viewer, and enter that string into the **License** field on the **Site Management | License** page.

Note: The Document Viewer page is visible in the Administration Menu | Services and Components menu once your Document Viewer is licensed.

12. If for any reason you want to change your Document Viewer configuration, go to **Administration Menu | Services and Components | Document Viewer**.

Note: For any change to take effect, you must restart the PrizmDoc Server service and then restart DocuShare.

Installation on a Linux server

1. Log into your DocuShare server as a UNIX server administrator (root).
2. In a terminal window, go to **<DSHome>/bin** and enter **stop_docushare.sh -q**.
3. Download, or copy, the DocuShare 7 Document Viewer add-on software to a temporary folder on your server, and decompress the file.
4. Open the folder, then locate and double-click **dsInstall**. Be patient; it takes several minutes before the system displays the first install Wizard screen.
5. Once the install Wizard begins, follow the onscreen instructions. Click **Next** to proceed or click **Back** to return to a previous screen.
6. When asked to select an update, check the appropriate add-on by selecting **Install DocuShare Document Viewer**, and then click **Next** to start the installation.
7. In the **PrizmDoc Config** window, enter the corresponding values in the displayed fields (refer to table above), and then click **Confirm**.
8. When the installation successfully completes, click **Finish** to close the installer.
9. In a terminal window, go to **<DSHome>/bin** and enter **start_docushare.sh** to start DocuShare, or enter **start_docushare.sh console** to view the log on the console.
10. Use a browser to connect to your site, and log in as an Administrator.
11. Obtain a new site license string that includes the Document Viewer, and enter that string into the **License** field on the **Site Management | License** page.

Note: The Document Viewer page is visible in the Administration Menu | Services and Components menu once your Document Viewer is licensed.

12. If for any reason you want to change your Document Viewer configuration, go to **Administration Menu | Services and Components | Document Viewer**.

Note: For any change to take effect, you must restart the PrizmDoc Server service and then restart DocuShare.