




FreeFlow Accxes HP-GL/2 Printer Driver Customer Release Notes Version 12.7.3

Contents

- 2 Release Content
- 3 New or Changed in this Release
- 4 Known Issues
- 5 Printer Driver Installation

July, 2008



FreeFlow Accxes HPGL/2 Driver Customer Release Notes

Version 12.7.3

Release Content

This 12.7.3 release is provided as a compressed zip file. English, German, French, Italian, Spanish, Portuguese and Russian languages are contained within each driver. The Windows XP and Server 2003 drivers are signed by Microsoft®, the Windows 2000, Vista and Server 2008 drivers are not signed.

Printer(s)	Operating System	Signed by Microsoft	Driver File Name
510	Server 2003	Yes	ACCXES_12_7_3_500_2K3.zip
510	Server 2003 x64	Yes	ACCXES_12_7_3_500_2K3x64.zip
510	Server 2008	No	ACCXES_12_7_3_500_2K8.zip
510	Server 2008 x64	No	ACCXES_12_7_3_500_2K8x64.zip
510	Vista	No	ACCXES_12_7_3_500_Vista.zip
510	Vista x64	No	ACCXES_12_7_3_500_Vistax64.zip
510	XP	Yes	ACCXES_12_7_3_500_XP.zip
510	XP x64	Yes	ACCXES_12_7_3_500_XPx64.zip
510	2000, Server 2000	No	ACCXES_12_7_3_500_2K.zip
721p	Server 2003	Yes	ACCXES_12_7_3_700_2K3.zip
721p	Server 2003 x64	Yes	ACCXES_12_7_3_700_2K3x64.zip
721p	Server 2008	No	ACCXES_12_7_3_700_2K8.zip
721p	Server 2008 x64	No	ACCXES_12_7_3_700_2K8x64.zip
721p	Vista	No	ACCXES_12_7_3_700_Vista.zip
721p	Vista x64	No	ACCXES_12_7_3_700_Vistax64.zip
721p	XP	Yes	ACCXES_12_7_3_700_XP.zip
721p	XP x64	Yes	ACCXES_12_7_3_700_XPx64.zip
721p	2000, Server 2000	No	ACCXES_12_7_3_700_2K.zip
6030,6050,6204,6050A	Server 2003	Yes	ACCXES_12_7_3_6000_2K3.zip
6030,6050,6204,6050A	Server 2003 x64	Yes	ACCXES_12_7_3_6000_2K3x64.zip
6030,6050,6204,6050A	Server 2008	No	ACCXES_12_7_3_6000_2K8.zip
6030,6050,6204,6050A	Server 2008 x64	No	ACCXES_12_7_3_6000_2K8x64.zip
6030,6050,6204,6050A	Vista	No	ACCXES_12_7_3_6000_Vista.zip
6030,6050,6204,6050A	Vista x64	No	ACCXES_12_7_3_6000_Vistax64.zip
6030,6050,6204,6050A	XP	Yes	ACCXES_12_7_3_6000_XP.zip
6030,6050,6204,6050A	XP x64	Yes	ACCXES_12_7_3_6000_XPx64.zip
6030,6050,6204,6050A	2000, Server 2000	No	ACCXES_12_7_3_6000_2K.zip

New or Changed in this Release

The following is new or changed since HP-GL/2 driver version 12.5.2

- Support for Windows Server 2008 has been added.
- Support for IPv6 on Windows Vista and Server 2008 has been added.
- There are two Finisher File Creator Utilities
 - The existing one, XESFin.exe is for use with Windows 2000, only supports IPV4
 - The new one is XFASFin.exe and is for Windows XP and newer versions of Windows.
 - For XP and newer versions of Windows, you must use XFASFin.exe to create .FIN files and add finishers.
 - XFASFin.exe supports both IPV4 and IPV6; it's version number is 12.7.1.0818.
 - This is available for download in the support & drivers section of www.xerox.com.
- Windows XP and Server 2003 drivers are signed by Microsoft.
- Windows 2000, Vista and Server 2008 drivers are not signed by Microsoft.
- Bugs fixed.
- Improved performance and port communications.
- You do not need to remove printer drivers that are version 12.5.2 or older. This 12.7.3 driver can co-exist with versions 12.5.2 and older.
- You do need to remove printer drivers that are version 12.5.4 or newer. This 12.7.3 driver cannot co-exist with versions 12.5.4 and newer.

Known Issues

Un-translated help

The OK, CANCEL and CLOSE(user-defined media) have help in English. The help for the accounting dialogs is in English.

Last Active Tab

The Last Active Tab feature does not work from within applications; this is a limitation of Windows.

Vista and Server 2008 Help

The “?” button in the tabs and dialogs is not supported in Vista and Server 2008. However, selecting a control and pressing F1 will bring up the help (for controls which the user can interact with).

User defined media sizes

You cannot save a user defined size within an application. The user defined size has to be created and saved in the driver's printing preferences.

Internet Protocol version 6

This is only recommended with Microsoft Windows Vista and Microsoft Server 2008. It is not supported in Windows XP.

Printer Driver Installation

New driver install:

Follow the procedure in the Xerox Wide Format with FreeFlow Accxes clients & drivers installation guide.

Existing drivers:

All previous versions of Wide Format HP-GL/2 drivers must be removed from the server and/or workstation client before installing this new driver, which includes; deleting the printer icon, deleting any xes net ports, removing the driver and then rebooting the operating system. Then, follow the procedure in the Xerox Wide Format with FreeFlow Accxes clients & drivers installation guide.

Using Standard TCP/IPv6

This driver supports the use of IPv6 on Vista and Server 2008.

You must use the new version of the fin file creator tool for IPv6 address and names when adding finishers.

Windows Printer Test Page

Additional files used by this driver.

Name	German	English	Spanish	French	Italian	Portuguese	Russian
XFARes.DLL	12.7.3.1475	12.7.3.2035	12.7.3.1461	12.7.3.1357	12.7.3.1461	12.7.3.1357	12.7.3.1460

Windows Printing Preferences>About Tab

You can also verify the driver file versions by looking on the About Tab in Printing Preferences.

Language	Version
German	12.7.3.2910 / 12.7.3.3898 / 12.7.3.1475
English	12.7.3.2910 / 12.7.3.3898 / 12.7.3.2035
Spanish	12.7.3.2910 / 12.7.3.3898 / 12.7.3.1461
French	12.7.3.2910 / 12.7.3.3898 / 12.7.3.1357
Italian	12.7.3.2910 / 12.7.3.3898 / 12.7.3.1461
Portuguese	12.7.3.2910 / 12.7.3.3898 / 12.7.3.1357
Russian	12.7.3.2910 / 12.7.3.3898 / 12.7.3.1460

Prepared by:
Xerox Corporation
800 Phillips Road
Building 139-26A
Webster, New York 14580-9791
USA

©XEROX Corporation. 2008. All rights reserved.

XEROX®, the sphere of connectivity design, XEROX Wide Format 6204, 6030, 6050, 6050A, 510, 721, 8825, 8830, 8850, Xerox Wide Format Scan System, FreeFlow® Accxes®, and acronyms, are trademarks of Xerox Corporation in the United States and/or other countries.

07/2008